

How to use Cisco Router as DHCP Server?





About Dynamic Host Configuration Protocol (DHCP) and how to use Cisco Router as DHCP Server

An upgrade of BOOTSTRAP PROTOCOL created by IETF (Internet Engineering Task Force). It is a clientserver protocol whose main objective is to assign IP-Address to the client asking for it, however DHCP also provides some more information than just IP-address. It reduces need of administrator to give IP-Address to all the devices statically and human errors can also be reduced with DHCP in a large network. Blog Image

Image not found or type unknown

What is DHCP?

It is an application layer protocol which provides IP-address, subnet-mask, default-gateway, DNS server IP-Address automatically. it uses UDP port no 67 and 68 as an information of transport layer of OSI.

How DHCP works?

DHCP works on DORA process

- DISCOVER
- OFFER
- REQUEST
- ACKNOWLEDGEMENT

DISCOVER

When client boots up it sends a broadcast looking for DHCP server and asking for IP-Address.

B4

Image not found or type unknown

OFFER

When server respond on discover message it sends an offer message this message is unicasted on the same IPaddress which is been offered by the server from the pool of a IP-address stored in server. Note: Cisco router as a DHCP server may do broadcast in this case.

Image not found or type unknown **REQUEST**

Client requests for the IP-address after checking it for IP conflicts. It is again a broadcast message from client to server, requesting for the same IP offered in the offer message.

Image not found or type unknown ACKNOWLEDGEMENT

It is a message sent by a server to the client as an acknowledgement that one IP--address is been assigned to client from the pool of IP-addresses. It is a uni-cast message.

Image not found or type unknown

Note: Cisco router as a DHCP server may do broadcast in this case.

These messages are all unicasted by DHCP helping agent when DHCP server is not in same broadcast domain.

We can make different devices as a DHCP server. Devices like Routers, Layer3 switches, Access-Points, modem, etc.

DHCP configuration on Cisco Router used as a DHCP server and client as a PC.

IP-Address pool =172.20.10.0/28

Subnet mask = 255.255.255.240

Default-gateway = 172.20.10.1

DNS server = 172.20.10.1

On R1

After assigning IP-Address on interface fastethernet 0/0 statically

DHCP as a router

Syntax:

R1(config)#ip dhcp excluded-address 172.20.10.1

With this command we exclude that IP-Address or range of IP-Addresses which are not to be provided to client via DHCP.

R1(config)#ip dhcp pool Network Bulls

With this we created dhcp pool and named it Network Bulls.

R1(dhcp-config)#network 172.20.10.0 255.255.250.240

This command is of dhcp mode in which we declare the IP subnet from where server will assign IP-Address.

R1(dhcp-config)#default-router 172.20.10.1

This command is telling about the default-gateway IP-Address.

R1(dhcp-config)#dns-server 172.20.10.1 This command is telling about the dns-server's IP-Address.

On PC

Open command prompt check IP-Address.

Syntax:

>ipconfig

One can also refer to RFC 2131 for DHCP

RFC 2131 was updated in 2014

Vishwajeet Rathore

Sr. Trainer - Cisco R&S and Security

Network Bulls

Image not found or type unknown

